

# Certified Seed

## Guide A-131

Charles R. Glover, Extension Agronomist

Cooperative Extension Service  
College of Agriculture and  
Home Economics



This publication is scheduled to be updated and reissued 8/01.

The cost of planting quality Certified seed represents only 1-1/2 to 2 percent of the total production cost of most crops. Quality seed represents the basic building block for good crop production. Considering the importance of quality seed, how can a farmer afford to plant anything but the best? The reduced yield from poor quality seed can cost much more than any additional cost for Certified seed.

Seed that carries the Certified tag often costs more than other seed, but you get what you pay for. The Certified tag assures that the seed meets the standards and requirements of the official seed certifying agency in the state it is grown. All official seed certifying agencies belong to the Association of Official Seed Certifying Agencies (AOSCA), which establishes minimum standards for each crop. The individual certifying agency may set higher standards than AOSCA, but never lower.

### Certifying Process

The certification process requires that the crop must pass both field inspection and laboratory analysis. The field must be planted from the proper class of seed, have adequate isolation, be planted in clean fields, and be free of objectionable weeds and diseases.

There are generally four classes of seed in the certification process. These are Breeder, Foundation, Registered, and Certified. Breeder seed, the true variety, is the highest class seed and comes directly from the plant breeder. The next highest class is Foundation seed. This seed is grown from Breeder seed. Registered seed, grown from Foundation seed, is the next highest class of seed. Certified seed is grown from either Foundation or Registered seed. Often the Registered class is omitted leaving three classes: Breeder, Foundation, and Certified.

Once the field has passed inspection, a sample of the seed must be sent to an official seed laboratory for analysis. The analysis tests include germination and purity. Purity is the percentage of pure seed, other crop seed, weed seed, and inert matter (dirt, stems, broken seeds, etc.). The seed must meet the standards set by the official seed certifying agency.

### Understanding the Analysis Tag

Seed that has passed the field inspection and the laboratory analysis can be tagged as Certified seed. In addition to the Certified tag there must also be an analysis tag. The analysis is most often printed on the back of the Certified tag, but it may also be a separate tag. Regardless of how the analysis is presented, it must contain the following information.

The first items are kind and variety. *Kind* refers to the crop, for example cotton, alfalfa, or corn. The *variety* must also be stated. The seed can be traced back to the field by the lot number and the name of the producer, which also must be included on the tag.

*Purity* is the percentage of pure seed. A high percentage of pure seed is required for crop seed, but some chaffy grasses and native plants may have a lower percent purity. A high pure seed percentage will provide the best results.

*Other crop seed* is given as a percentage of the total weight of the package. Other crop seed may be allowed in very small percentages and still be eligible for certification. Choose seed with a near-zero percentage of other crop seed.

*Inert matter* is the non-viable material in the bag, such as sand, stones, sticks, dirt, chaff, broken seeds, and vegetative materials. These materials do not increase yield and one should look

for and expect a very low percentage of inert matter in Certified seed.

*Weed seeds* must also be given in percentage of the total weight. Tolerance for objectionable and noxious weeds is generally zero. Other weed seeds may be present but only in very low percentages.

*Germination percentage* is the percentage of pure seed that will produce normal plants when planted under favorable conditions. One can determine the percent of pure live seed by multiplying the pure seed percentage times the germination percentage and dividing by 100. For example, you have a lot of seed with 95.5 percent pure seed and 93 percent germination. The pure live seed is 88.82 percent. The value of the seed

can be determined by the percentage of pure live seed.

Some crops such as legumes often have a percentage of *hard seed*. Hard seed does not germinate in the prescribed time because the hard seed coat prevents or delays water penetration into the seed. Hard seed is undesirable when early germination is required. However, it can be desirable when an extended germination period could improve the chances of getting a good stand.

Don't cut corners with seed costs. Seed is the basis for crop production and poor-quality seed can result in reduction in yield and quality of your crop.

Quality does not cost—it pays.